

Extended Window Manager Hints

X Desktop Group(<http://www.freedesktop.org>)

Version 1.2
October 7, 2002

Table of Contents

1. Introduction.....	1
2. Non-ICCCM features	2
3. Root Window Properties (and Related Messages).....	6
4. Other Root Window Messages.....	11
5. Application Window Properties	13
6. Window Manager Protocols	20
7. Implementation notes	20
8. References.....	25
9. Copyright.....	25
10. Contributors	26
11. Change history	26

1. Introduction

1.1. Version

This is Version 1.2 of the Extended Window Manager Hints (EWMH) spec, updated October 7, 2002.

1.2. What is this spec?

This spec defines interactions between window managers, applications, and the utilities that form part of a desktop environment. It builds on the Inter-Client Communication Conventions Manual [ICCCM], which defines window manager interactions at a lower level. The ICCCM does not provide ways to implement many features that modern desktop users expect. The GNOME and KDE desktop projects originally developed their own extensions to the ICCCM to support these features; this spec replaces those custom extensions with a standardized set of ICCCM additions that any desktop environment can adopt.

1.3. Language used in this specification

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in RFC 2119.

The key words "Window Manager" refer to a window manager which is adopting this specification. "Pager" refers to desktop utility applications, including pagers and taskbars. "Application" refers to other clients. "Clients" refers to Pagers and Applications ie. all X clients, except for the Window Manager.

1.4. Prerequisites for adoption of this specification

Window Managers and Clients which aim to fulfill this specification MUST adhere to the ICCCM on which this specification builds. If this specification explicitly modifies the ICCCM Window Managers and Clients MUST fulfill these modifications.

2. Non-ICCCM features

There is a number of window management features or behaviors which are not specified in the ICCCM, but are commonly met in modern window managers and desktop environments.

2.1. Additional States

The ICCCM allows window managers to implement additional window states, which will appear to clients as substates of NormalState and IconicState. Two commonly met examples are Maximized and Shaded. A window manager may implement these as proper substates of NormalState and IconicState, or it may treat them as independent flags, allowing e.g. a maximized window to be iconified and to re-appear as maximized upon de-iconification.

2.1.1. Maximization

Maximization is a very old feature of window managers. There was even a ZoomedState in early ICCCM drafts. Maximizing a window should give it as much of the screen area as possible (this may not be the full screen area, but only a smaller 'workarea', since the window manager may have reserved certain areas for other windows). A window manager is expected to remember the geometry of a maximized window and restore it upon de-maximization. Modern window managers typically allow separate horizontal and vertical maximization.

With the introduction of the Xinerama extension in X11 R6.4, maximization has become more involved. Xinerama allows a screen to span multiple monitors in a freely configurable geometry. In such a setting, maximizing a window would ideally not grow it to fill the whole screen, but only the monitor it is shown on. There are of course borderline cases for windows crossing monitor boundaries, and 'real' maximization to the full screen may sometimes be useful.

2.1.2. Shading

Some desktop environments offer shading (also known as rollup) as an alternative to iconification. A shaded window typically shows only the titlebar, the client window is hidden, thus shading is not useful for windows which are not decorated with a titlebar.

2.2. Modality

The WM_TRANSIENT_FOR hint of the ICCCM allows clients to specify that a toplevel window may be closed before the client finishes. A typical example of a transient window is a dialog. Some dialogs can be open for a long time, while the user continues to work in the main window. Other dialogs have to be closed before the user can continue to work in the main window. This property is called modality. While clients can implement modal windows in an ICCCM compliant way using the globally active input model, some window managers offer support for handling modality.

2.3. Large Desktops

The window manager may offer to arrange the managed windows on a desktop that is larger than the root window. The screen functions as a viewport on this large desktop. Different policies regarding the positioning of the viewport on the desktop can be implemented: The window manager may only allow the viewport position to change in increments of the screen size (paging) or it may allow arbitrary positions (scrolling).

To fulfill the ICCCM principle that clients should behave the same regardless whether a window manager is running or not, window managers which implement large desktops must interpret all client-provided geometries with respect to the current viewport.

2.3.1. Implementation note

There are two options for implementing a large desktop: The first is to keep the managed windows (or, if reparenting, their frames) as children of the root window. Moving the viewport is achieved by moving all managed windows in the opposite direction.

The second alternative is to reparent all managed windows to a dedicated large window (somewhat inappropriately called a 'virtual root'). Moving the viewport is then achieved by moving the virtual root in the opposite direction.

Both alternatives are completely ICCCM compliant, although the second one may be somewhat problematic for clients trying to figure out the window manager decorations around their toplevel windows and for clients trying to draw background images on the root window.

2.4. Sticky windows

A window manager which implements a large desktop typically offers a way for the user to make certain windows 'stick to the glass', i.e. these windows will stay at the same position on the screen when the viewport is moved.

2.5. Virtual Desktops

Most X servers have only a single screen. The window manager may virtualize this resource and offer multiple so-called 'virtual desktops', of which only one can be shown on the screen at a time. There is some variation among the features of virtual desktop implementations. There may be a fixed number of desktops, or new ones may be created dynamically. The size of the desktops may be fixed or variable. If the desktops are larger than the root window, their viewports (see Section 2.3) may be independent or forced to be at the same position.

A window manager which implements virtual desktops generally offers a way for the user to move clients between desktops. Clients may be allowed to occupy more than one desktop simultaneously.

2.5.1. Implementation note

There are at least two options for implementing virtual desktops. The first is to use multiple virtual roots (see Section 2.3.1) and change the current desktop by manipulating the stacking order of the virtual roots. This is completely ICCCM compliant, but has the issues outlined in Section 2.3.1

The second option is to keep all managed windows as children of the root window and unmap the frames of those which are not on the current desktop. Unmapped windows should be placed in `IconicState`, according to the ICCCM. Windows which are actually iconified or minimized should have the `_NET_WM_STATE_HIDDEN` property set, to communicate to pagers that the window should not be represented as "onscreen."

2.6. Pagers

A pager offers a different UI for window management tasks. It shows a miniature view of the desktop(s) representing managed windows by small rectangles and allows the user to initiate various window manager actions by manipulating these representations. Typically offered actions are activation (see Section 2.8), moving, restacking, iconification, maximization and closing. On a large desktop, the pager may offer a way to move the viewport. On virtual desktops, the pager may offer ways to move windows between desktops and to change the current desktop.

2.7. Taskbars

A taskbar offers another UI for window management tasks. It typically represents client windows as a list of buttons labelled with the window titles and possibly icons. Pressing a button initiates a window manager action on the represented window, typical actions being activation and iconification. In environments with a taskbar, icons are often considered inappropriate, since the iconified windows are already represented in the taskbar.

2.8. Activation

In the X world, activating a window means to give it the input focus. This may not be possible if the window is unmapped, because it is on a different desktop. Thus, activating a window may involve

additional steps like moving it to the current desktop (or changing to the desktop the window is on), deiconifying it or raising it.

2.9. Animated iconification

Some window managers display some form of animation when (de-)iconifying a window. This may be a line drawing connecting the corners of the window with the corners of the icon or the window may be opaquely moved and resized on some trajectory joining the window location and the icon location.

2.10. Window-in-window MDI

Window-in-window MDI is a multiple document interface known from MS Windows platforms. Programs employing it have a single top-level window which contains a workspace which contains the subwindows for the open documents. These subwindows are decorated with window manager frames and can be manipulated within their parent window just like ordinary top-level windows on the root window.

2.11. Layered stacking order

Some window managers keep the toplevel windows not in a single linear stack, but subdivide the stack into several layers. There is a lot of variation among the features of layered stacking order implementations. The number of layers may or may not be fixed. The layer of a toplevel window may be explicit and directly modifiable or derived from other properties of the window, e.g. the *type* of the window. The stacking order may or may not be strict, i.e. not allow the user to raise or lower windows beyond their layer.

2.12. Scope of this spec

This spec tries to address the following issues:

- Allow clients to influence their initial state with respect to maximization, shading, stickiness, desktop, stacking order.
- Improve the window managers ability to vary window decorations and maintain the stacking order by allowing clients to hint the window manager about the type of their windows.
- Enable pagers and taskbars to be implemented as separate clients and allow them to work with any compliant window manager.

This spec doesn't cover any of the following:

- Other IPC mechanisms like ICE or Corba.
- Window manager configuration.
- Window manager documentation.
- Clients appearing on a proper subset of desktops.

- Window-in-window MDI.

The window manager is supposed to be in charge of window management policy, so that there is consistent behavior on the user's screen no matter who wrote the clients.

The spec offers a lot of external control about window manager actions. This is intended mainly to allow pagers, taskbars and similar window manager UIs to be implemented as separate clients. "Ordinary" clients shouldn't use these except maybe in response to a direct user request (i.e. setting a config option to start maximized or specifying a `-desk n` command line argument).

3. Root Window Properties (and Related Messages)

Whenever this spec speaks about "sending a message to the root window", it is understood that the client is supposed to create a `ClientMessage` event with the specified contents and send it by using a `SendEvent` request with the following arguments:

<code>destination</code>	<code>root</code>
<code>propagate</code>	<code>False</code>
<code>event-mask</code>	<code>(SubstructureNotify SubstructureRedirect)</code>
<code>event</code>	the specified <code>ClientMessage</code>

3.1. `_NET_SUPPORTED`

```
_NET_SUPPORTED, ATOM[]/32
```

This property **MUST** be set by the Window Manager to indicate which hints it supports. For example: considering `_NET_WM_STATE` both this atom and all supported states e.g.

`_NET_WM_STATE_MODAL`, `_NET_WM_STATE_STICKY`, would be listed. This assumes that backwards incompatible changes will not be made to the hints (without being renamed).

3.2. `_NET_CLIENT_LIST`

```
_NET_CLIENT_LIST, WINDOW[]/32  
_NET_CLIENT_LIST_STACKING, WINDOW[]/32
```

These arrays contain all X Windows managed by the Window Manager. `_NET_CLIENT_LIST` has initial mapping order, starting with the oldest window. `_NET_CLIENT_LIST_STACKING` has bottom-to-top stacking order. These properties **SHOULD** be set and updated by the Window Manager.

3.3. `_NET_NUMBER_OF_DESKTOPS`

```
_NET_NUMBER_OF_DESKTOPS, CARDINAL/32
```

This property **SHOULD** be set and updated by the Window Manager to indicate the number of virtual desktops.

A Pager can request a change in the number of desktops by sending a `_NET_NUMBER_OF_DESKTOPS` message to the root window:

```
_NET_NUMBER_OF_DESKTOPS
message_type = _NET_NUMBER_OF_DESKTOPS
format = 32
data.l[0] = new_number_of_desktops
```

The Window Manager is free to honor or reject this request. If the request is honored `_NET_NUMBER_OF_DESKTOPS` **MUST** be set to the new number of desktops, `_NET_VIRTUAL_ROOTS` **MUST** be set to store the new number of desktop virtual root window IDs and `_NET_DESKTOP_VIEWPORT` and `_NET_WORKAREA` must also be changed accordingly. The `_NET_DESKTOP_NAMES` property **MAY** remain unchanged.

If the number of desktops is shrinking and `_NET_CURRENT_DESKTOP` is out of the new range of available desktops, then this **MUST** be set to the last available desktop from the new set. Clients that are still present on desktops that are out of the new range **MUST** be moved to the very last desktop from the new set. For these `_NET_WM_DESKTOP` **MUST** be updated.

3.4. `_NET_DESKTOP_GEOMETRY`

```
_NET_DESKTOP_GEOMETRY width, height, CARDINAL[2]/32
```

Array of two cardinals that defines the common size of all desktops (this is equal to the screen size if the Window Manager doesn't support large desktops, otherwise it's equal to the virtual size of the desktop). This property **SHOULD** be set by the Window Manager.

A Pager can request a change in the desktop geometry by sending a `_NET_DESKTOP_GEOMETRY` client message to the root window:

```
_NET_DESKTOP_GEOMETRY
message_type = _NET_DESKTOP_GEOMETRY
format = 32
data.l[0] = new_width
data.l[1] = new_height
```

The Window Manager **MAY** choose to ignore this message, in which case `_NET_DESKTOP_GEOMETRY` property will remain unchanged.

3.5. `_NET_DESKTOP_VIEWPORT`

```
_NET_DESKTOP_VIEWPORT x, y, CARDINAL[][2]/32
```

Array of pairs of cardinals that define the top left corner of each desktop's viewport. For Window Managers that don't support large desktops, this **MUST** always be set to (0,0).

A Pager can request to change the viewport for the current desktop by sending a `_NET_DESKTOP_VIEWPORT` client message to the root window:

```
_NET_DESKTOP_VIEWPORT
message_type = _NET_DESKTOP_VIEWPORT
format = 32
data.l[0] = new_vx
data.l[1] = new_vy
```

The Window Manager MAY choose to ignore this message, in which case `_NET_DESKTOP_VIEWPORT` property will remain unchanged.

3.6. `_NET_CURRENT_DESKTOP`

```
_NET_CURRENT_DESKTOP desktop, CARDINAL/32
```

The index of the current desktop. This is always an integer between 0 and `_NET_NUMBER_OF_DESKTOPS - 1`. This MUST be set and updated by the Window Manager. If a Pager wants to switch to another virtual desktop, it MUST send a `_NET_CURRENT_DESKTOP` client message to the root window:

```
_NET_CURRENT_DESKTOP
message_type = _NET_CURRENT_DESKTOP
format = 32
data.l[0] = new_index
```

3.7. `_NET_DESKTOP_NAMES`

```
_NET_DESKTOP_NAMES, UTF8_STRING[ ]
```

The names of all virtual desktops. This is a list of NULL-terminated strings in UTF-8 encoding [UTF8]. This property MAY be changed by a Pager or the Window Manager at any time.

Note: The number of names could be different from `_NET_NUMBER_OF_DESKTOPS`. If it is less than `_NET_NUMBER_OF_DESKTOPS`, then the desktops with high numbers are unnamed. If it is larger than `_NET_NUMBER_OF_DESKTOPS`, then the excess names outside of the `_NET_NUMBER_OF_DESKTOPS` are considered to be reserved in case the number of desktops is increased.

Rationale: The name is not a necessary attribute of a virtual desktop. Thus the availability or unavailability of names has no impact on virtual desktop functionality. Since names are set by users and users are likely to preset names for a fixed number of desktops, it doesn't make sense to shrink or grow this list when the number of available desktops changes.

3.8. `_NET_ACTIVE_WINDOW`

```
_NET_ACTIVE_WINDOW, WINDOW/32
```


The window ID of the currently active window or None if no window has the focus. This is a read-only property set by the Window Manager. If a Client wants to activate another window, it **MUST** send a `_NET_ACTIVE_WINDOW` client message to the root window:

```
_NET_ACTIVE_WINDOW
window = window to activate
message_type = _NET_ACTIVE_WINDOW
format = 32
data.l[0] = 0 /* may be used later */
```

3.9. `_NET_WORKAREA`

```
_NET_WORKAREA, x, y, width, height CARDINAL[][4]/32
```

This property **MUST** be set by the Window Manager upon calculating the work area for each desktop. Contains a geometry for each desktop. These geometries are specified relative to the viewport on each desktop and specify an area that is completely contained within the viewport. Work area **SHOULD** be used by desktop applications to place desktop icons appropriately.

The Window Manager **SHOULD** calculate this space by taking the current page minus space occupied by dock and panel windows, as indicated by the `_NET_WM_STRUT` property set on client windows.

3.10. `_NET_SUPPORTING_WM_CHECK`

```
_NET_SUPPORTING_WM_CHECK, WINDOW/32
```

The Window Manager **MUST** set this property on the root window to be the ID of a child window created by himself, to indicate that a compliant window manager is active. The child window **MUST** also have the `_NET_SUPPORTING_WM_CHECK` property set to the ID of the child window. The child window **MUST** also have the `_NET_WM_NAME` property set to the name of the Window Manager.

Rationale: The child window is used to distinguish an active Window Manager from a stale `_NET_SUPPORTING_WM_CHECK` property that happens to point to another window. If the `_NET_SUPPORTING_WM_CHECK` window on the client window is missing or not properly set, clients **SHOULD** assume that no conforming Window Manager is present.

3.11. `_NET_VIRTUAL_ROOTS`

```
_NET_VIRTUAL_ROOTS, WINDOW[]/32
```

To implement virtual desktops, some Window Managers reparent client windows to a child of the root window. Window Managers using this technique **MUST** set this property to a list of IDs for windows that are acting as virtual root windows. This property allows background setting programs to work with virtual roots and allows clients to figure out the window manager frame windows of their windows.

3.12. _NET_DESKTOP_LAYOUT

```
_NET_DESKTOP_LAYOUT, orientation, x, y, starting_corner CARDINAL[4]/32
#define _NET_WM_ORIENTATION_HORZ 0
#define _NET_WM_ORIENTATION_VERT 1

#define _NET_WM_TOPLEFT 0
#define _NET_WM_TOPRIGHT 1
#define _NET_WM_BOTTOMRIGHT 2
#define _NET_WM_BOTTOMLEFT 3
```

This property is set by a Pager, not by the Window Manager. When setting this property, the Pager must own a manager selection (as defined in the ICCCM 2.8). The manager selection is called `_NET_DESKTOP_LAYOUT_Sn` where `n` is the screen number. The purpose of this property is to allow the Window Manager to know the desktop layout displayed by the Pager.

`_NET_DESKTOP_LAYOUT` describes the layout of virtual desktops relative to each other. More specifically, it describes the layout used by the owner of the manager selection. The Window Manager may use this layout information or may choose to ignore it. The property contains four values: the Pager orientation, the number of desktops in the X direction, the number in the Y direction, and the starting corner of the layout, i.e. the corner containing the first desktop.

Note: In order to inter-operate with Pagers implementing an earlier draft of this document, Window Managers should accept a `_NET_DESKTOP_LAYOUT` property of length 3 and use `_NET_WM_TOPLEFT` as the starting corner in this case.

The virtual desktops are arranged in a rectangle with `X` rows and `Y` columns. If `X` times `Y` does not match the total number of desktops as specified by `_NET_NUMBER_OF_DESKTOPS`, the highest-numbered workspaces are assumed to be nonexistent. Either `X` or `Y` (but not both) may be specified as 0 in which case its actual value will be derived from `_NET_NUMBER_OF_DESKTOPS`.

When the orientation is `_NET_WM_ORIENTATION_HORZ` the desktops are laid out in rows, with the first desktop in the specified starting corner. So a layout with `X=4` and `Y=3` starting in the `_NET_WM_TOPLEFT` corner looks like this:

```
+---+---+---+---+
| 0 | 1 | 2 | 3 |
+---+---+---+---+
| 4 | 5 | 6 | 7 |
+---+---+---+---+
| 8 | 9 |10|11|
+---+---+---+---+
```

With starting_corner `_NET_WM_BOTTOMRIGHT`, it looks like this:

```
+---+---+---+---+
|11|10| 9| 8|
+---+---+---+---+
| 7| 6| 5| 4|
+---+---+---+---+
| 3| 2| 1| 0|
+---+---+---+---+
```

When the orientation is `_NET_WM_ORIENTATION_VERT` the layout for `X=4` and `Y=3` starting in the `_NET_WM_TOPLEFT` corner looks like:

```
+---+---+---+---+
| 0| 3| 6| 9|
+---+---+---+---+
| 1| 4| 7|10|
+---+---+---+---+
| 2| 5| 8|11|
+---+---+---+---+
```

With starting_corner `_NET_WM_TOPRIGHT`, it looks like:

```
+---+---+---+---+
| 9| 6| 3| 0|
+---+---+---+---+
|10| 7| 4| 1|
+---+---+---+---+
|11| 8| 5| 2|
+---+---+---+---+
```

The numbers here are the desktop numbers, as for `_NET_CURRENT_DESKTOP`.

3.13. `_NET_SHOWING_DESKTOP`

`_NET_SHOWING_DESKTOP desktop, CARDINAL/32`

Some Window Managers have a "showing the desktop" mode in which windows are hidden, and the desktop background is displayed and focused. If a Window Manager supports the `_NET_SHOWING_DESKTOP` hint, it MUST set it to a value of 1 when the Window Manager is in "showing the desktop" mode, and a value of zero if the Window Manager is not in this mode.

If a Pager wants to enter or leave the mode, it MUST send a `_NET_SHOWING_DESKTOP` client message to the root window requesting the change:

```
_NET_SHOWING_DESKTOP
message_type = _NET_SHOWING_DESKTOP
format = 32
data.l[0] = boolean 0 or 1
```

The Window Manager may choose to ignore this client message.

4. Other Root Window Messages

4.1. _NET_CLOSE_WINDOW

`_NET_CLOSE_WINDOW`

Pagers wanting to close a window MUST send a `_NET_CLOSE_WINDOW` client message request to the root window:

```
_NET_CLOSE_WINDOW
window = window to close
message_type = _NET_CLOSE_WINDOW
format = 32
data.l[0] = 0 /* may be used later */
```

The Window Manager MUST then attempt to close the window specified.

Rationale: A Window Manager might be more clever than the usual method (send `WM_DELETE` message if the protocol is selected, `XKillClient` otherwise). It might introduce a timeout, for example. Instead of duplicating the code, the Window Manager can easily do the job.

4.2. _NET_MOVERESIZE_WINDOW

```
_NET_MOVERESIZE_WINDOW
window = window to be moved or resized
message_type = _NET_MOVERESIZE_WINDOW
format = 32
data.l[0] = gravity and flags
data.l[1] = x
data.l[2] = y
data.l[3] = width
data.l[4] = height
```

The low byte of `data.l[0]` contains the gravity to use; it may contain any value allowed for the `WM_SIZE_HINTS.win_gravity` property: NorthWest (1), North (2), NorthEast (3), West (4), Center (5), East (6), SouthWest (7), South (8), SouthEast (9) and Static (10). A gravity of 0 indicates that the Window Manager should use the gravity specified in `WM_SIZE_HINTS.win_gravity`. The bits 8 to 11 indicate the presence of x, y, width and height.

Pagers wanting to move or resize a window may send a `_NET_MOVERESIZE_WINDOW` client message request to the root window instead of using a `ConfigureRequest`.

Window Managers should treat a `_NET_MOVERESIZE_WINDOW` message exactly like a `ConfigureRequest` (in particular, adhering to the ICCCM rules about synthetic `ConfigureNotify` events), except that they should use the gravity specified in the message.

Rationale: Using a `_NET_MOVERESIZE_WINDOW` message with `StaticGravity` allows Pagers to exactly position and resize a window including its decorations without knowing the size of the decorations.

4.3. _NET_WM_MOVERESIZE

```

_NET_WM_MOVERESIZE
    window = window to be moved or resized
    message_type = _NET_WM_MOVERESIZE
    format = 32
    data.l[0] = x_root
    data.l[1] = y_root
    data.l[2] = direction
    data.l[3] = button

```

This message allows Clients to initiate window movement or resizing. They can define their own move and size "grips", whilst letting the Window Manager control the actual operation. This means that all moves/resizes can happen in a consistent manner as defined by the Window Manager.

When sending this message in response to a button press event, button **SHOULD** indicate the button which was pressed, x_root and y_root **MUST** indicate the position of the button press with respect to the root window and direction **MUST** indicate whether this is a move or resize event, and if it is a resize event, which edges of the window the size grip applies to. When sending this message in response to a key event, the direction **MUST** indicate whether this is a move or resize event and the other fields are unused.

```

#define _NET_WM_MOVERESIZE_SIZE_TOPLEFT      0
#define _NET_WM_MOVERESIZE_SIZE_TOP         1
#define _NET_WM_MOVERESIZE_SIZE_TOPRIGHT    2
#define _NET_WM_MOVERESIZE_SIZE_RIGHT       3
#define _NET_WM_MOVERESIZE_SIZE_BOTTOMRIGHT 4
#define _NET_WM_MOVERESIZE_SIZE_BOTTOM      5
#define _NET_WM_MOVERESIZE_SIZE_BOTTOMLEFT  6
#define _NET_WM_MOVERESIZE_SIZE_LEFT        7
#define _NET_WM_MOVERESIZE_MOVE              8    /* movement only */
#define _NET_WM_MOVERESIZE_SIZE_KEYBOARD     9    /* size via keyboard */
#define _NET_WM_MOVERESIZE_MOVE_KEYBOARD    10    /* move via keyboard */

```

The Client **MUST** release all grabs prior to sending such message.

The Window Manager can use the button field to determine the events on which it terminates the operation initiated by the _NET_WM_MOVERESIZE message. Since there is a race condition between a client sending the _NET_WM_MOVERESIZE message and the user releasing the button, Window Managers are advised to offer some other means to terminate the operation, e.g. by pressing the ESC key.

5. Application Window Properties

5.1. _NET_WM_NAME

```

_NET_WM_NAME, UTF8_STRING

```

The Client **SHOULD** set this to the title of the window in UTF-8 encoding. If set, the Window Manager should use this in preference to WM_NAME.

5.2. `_NET_WM_VISIBLE_NAME`

`_NET_WM_VISIBLE_NAME`, UTF8_STRING

If the Window Manager displays a window name other than `_NET_WM_NAME` the Window Manager **MUST** set this to the title displayed in UTF-8 encoding.

Rationale: This property is for Window Managers that display a title different from the `_NET_WM_NAME` or `WM_NAME` of the window (i.e. `xterm <1>`, `xterm <2>`, ... is shown, but `_NET_WM_NAME` / `WM_NAME` is still `xterm` for each window) thereby allowing Pagers to display the same title as the Window Manager.

5.3. `_NET_WM_ICON_NAME`

`_NET_WM_ICON_NAME`, UTF8_STRING

The Client **SHOULD** set this to the title of the icon for this window in UTF-8 encoding. If set, the Window Manager should use this in preference to `WM_ICON_NAME`.

5.4. `_NET_WM_VISIBLE_ICON_NAME`

`_NET_WM_VISIBLE_ICON_NAME`, UTF8_STRING

If the Window Manager displays an icon name other than `_NET_WM_ICON_NAME` the Window Manager **MUST** set this to the title displayed in UTF-8 encoding.

5.5. `_NET_WM_DESKTOP`

`_NET_WM_DESKTOP` desktop, CARDINAL/32

Cardinal to determine the desktop the window is in (or wants to be) starting with 0 for the first desktop. A Client **MAY** choose not to set this property, in which case the Window Manager **SHOULD** place it as it wishes. 0xFFFFFFFF indicates that the window **SHOULD** appear on all desktops.

The Window Manager should honor `_NET_WM_DESKTOP` whenever a withdrawn window requests to be mapped.

The Window Manager should remove the property whenever a window is withdrawn but it should leave the property in place when it is shutting down, e.g. in response to losing ownership of the `WM_Sn` manager selection.

Rationale: Removing the property upon window withdrawal helps legacy applications which want to reuse withdrawn windows. Not removing the property upon shutdown allows the next Window Manager to restore windows to their previous desktops.

A Client can request a change of desktop for a non-withdrawn window by sending a `_NET_WM_DESKTOP` client message to the root window:

`_NET_WM_DESKTOP`

```

window = the respective client window
message_type = _NET_WM_DESKTOP
format = 32
data.l[0] = new_desktop

```

The Window Manager MUST keep this property updated on all windows.

5.6. `_NET_WM_WINDOW_TYPE`

```
_NET_WM_WINDOW_TYPE, ATOM[]/32
```

This SHOULD be set by the Client before mapping to a list of atoms indicating the functional type of the window. This property SHOULD be used by the window manager in determining the decoration, stacking position and other behavior of the window. The Client SHOULD specify window types in order of preference (the first being most preferable) but MUST include at least one of the basic window type atoms from the list below. This is to allow for extension of the list of types whilst providing default behavior for Window Managers that do not recognize the extensions.

Rationale: This hint is intended to replace the MOTIF hints. One of the objections to the MOTIF hints is that they are a purely visual description of the window decoration. By describing the function of the window, the Window Manager can apply consistent decoration and behavior to windows of the same type. Possible examples of behavior include keeping dock/panels on top or allowing pinnable menus / toolbars to only be hidden when another window has focus (NextStep style).

```

_NET_WM_WINDOW_TYPE_DESKTOP, ATOM
_NET_WM_WINDOW_TYPE_DOCK, ATOM
_NET_WM_WINDOW_TYPE_TOOLBAR, ATOM
_NET_WM_WINDOW_TYPE_MENU, ATOM
_NET_WM_WINDOW_TYPE_UTILITY, ATOM
_NET_WM_WINDOW_TYPE_SPLASH, ATOM
_NET_WM_WINDOW_TYPE_DIALOG, ATOM
_NET_WM_WINDOW_TYPE_NORMAL, ATOM

```

`_NET_WM_WINDOW_TYPE_DESKTOP` indicates a desktop feature. This can include a single window containing desktop icons with the same dimensions as the screen, allowing the desktop environment to have full control of the desktop, without the need for proxying root window clicks.

`_NET_WM_WINDOW_TYPE_DOCK` indicates a dock or panel feature. Typically a Window Manager would keep such windows on top of all other windows.

`_NET_WM_WINDOW_TYPE_TOOLBAR` and `_NET_WM_WINDOW_TYPE_MENU` indicate toolbar and pinnable menu windows, respectively (i.e. toolbars and menus "torn off" from the main application). Windows of this type may set the `WM_TRANSIENT_FOR` hint indicating the main application window.

`_NET_WM_WINDOW_TYPE_UTILITY` indicates a small persistent utility window, such as a palette or toolbox. It is distinct from type `TOOLBAR` because it does not correspond to a toolbar torn off from the main application. It's distinct from type `DIALOG` because it isn't a transient dialog, the user will probably keep it open while they're working. Windows of this type may set the `WM_TRANSIENT_FOR` hint indicating the main application window.

`_NET_WM_WINDOW_TYPE_SPLASH` indicates that the window is a splash screen displayed as an application is starting up.

`_NET_WM_WINDOW_TYPE_DIALOG` indicates that this is a dialog window. If

`_NET_WM_WINDOW_TYPE` is not set, then windows with `WM_TRANSIENT_FOR` set **MUST** be taken as this type.

`_NET_WM_WINDOW_TYPE_NORMAL` indicates that this is a normal, top-level window. Windows with neither `_NET_WM_WINDOW_TYPE` nor `WM_TRANSIENT_FOR` set **MUST** be taken as this type.

5.7. `_NET_WM_STATE`

`_NET_WM_STATE`, `ATOM[]`

A list of hints describing the window state. Atoms present in the list **MUST** be considered set, atoms not present in the list **MUST** be considered not set. The Window Manager **SHOULD** honor `_NET_WM_STATE` whenever a withdrawn window requests to be mapped. A Client wishing to change the state of a window **MUST** send a `_NET_WM_STATE` client message to the root window (see below). The Window Manager **MUST** keep this property updated to reflect the current state of the window.

The Window Manager should remove the property whenever a window is withdrawn, but it should leave the property in place when it is shutting down, e.g. in response to losing ownership of the `WM_Sn` manager selection.

Rationale: Removing the property upon window withdrawal helps legacy applications which want to reuse withdrawn windows. Not removing the property upon shutdown allows the next Window Manager to restore windows to their previous state.

Possible atoms are:

```
_NET_WM_STATE_MODAL, ATOM
_NET_WM_STATE_STICKY, ATOM
_NET_WM_STATE_MAXIMIZED_VERT, ATOM
_NET_WM_STATE_MAXIMIZED_HORZ, ATOM
_NET_WM_STATE_SHADED, ATOM
_NET_WM_STATE_SKIP_TASKBAR, ATOM
_NET_WM_STATE_SKIP_PAGER, ATOM
_NET_WM_STATE_HIDDEN, ATOM
_NET_WM_STATE_FULLSCREEN, ATOM
_NET_WM_STATE_ABOVE, ATOM
_NET_WM_STATE_BELOW, ATOM
```

An implementation **MAY** add new atoms to this list. Implementations without extensions **MUST** ignore any unknown atoms, effectively removing them from the list. These extension atoms **MUST NOT** start with the prefix `_NET`.

`_NET_WM_STATE_MODAL` indicates that this is a modal dialog box. The `WM_TRANSIENT_FOR` hint **MUST** be set to indicate which window the dialog is a modal for, or set to the root window if the dialog is a modal for its window group.

`_NET_WM_STATE_STICKY` indicates that the Window Manager **SHOULD** keep the window's position fixed on the screen, even when the virtual desktop scrolls.

`_NET_WM_STATE_MAXIMIZED_{VERT,HORZ}` indicates that the window is {vertically,horizontally} maximized.

`_NET_WM_STATE_SHADED` indicates that the window is shaded.

`_NET_WM_STATE_SKIP_TASKBAR` indicates that the window should not be included on a taskbar. This hint should be requested by the application, i.e. it indicates that the window by nature is never in the taskbar. Applications should not set this hint if `_NET_WM_WINDOW_TYPE` already conveys the exact nature of the window.

`_NET_WM_STATE_SKIP_PAGER` indicates that the window should not be included on a Pager. This hint should be requested by the application, i.e. it indicates that the window by nature is never in the Pager. Applications should not set this hint if `_NET_WM_WINDOW_TYPE` already conveys the exact nature of the window.

`_NET_WM_STATE_HIDDEN` should be set by the Window Manager to indicate that a window would not be visible on the screen if its desktop/viewport were active and its coordinates were within the screen bounds. The canonical example is that minimized windows should be in the `_NET_WM_STATE_HIDDEN` state. Pagers and similar applications should use `_NET_WM_STATE_HIDDEN` instead of `WM_STATE` to decide whether to display a window in miniature representations of the windows on a desktop.

Implementation note: if an Application asks to toggle `_NET_WM_STATE_HIDDEN` the Window Manager should probably just ignore the request, since `_NET_WM_STATE_HIDDEN` is a function of some other aspect of the window such as minimization, rather than an independent state.

`_NET_WM_STATE_FULLSCREEN` indicates that the window should fill the entire screen and have no window decorations. For example, a presentation program would use this hint.

`_NET_WM_STATE_ABOVE` indicates that the window should be on top of most windows (see Section 7.10 for details).

`_NET_WM_STATE_BELOW` indicates that the window should be below most windows (see Section 7.10 for details).

`_NET_WM_STATE_ABOVE` and `_NET_WM_STATE_BELOW` are mainly meant for user preferences and should not be used by applications e.g. for drawing attention to their dialogs (the Urgency hint should be used in that case, see Section 7.4).'

To change the state of a mapped window, a Client MUST send a `_NET_WM_STATE` client message to the root window (window is the respective window, type `_NET_WM_STATE`, format 32, `l[0]`=<the action, as listed below>, `l[1]`=<First property to alter>, `l[2]`=<Second property to alter>). This message allows two properties to be changed simultaneously, specifically to allow both horizontal and vertical maximization to be altered together. `l[2]` MUST be set to zero if only one property is to be changed. `l[0]`, the action, MUST be one of:

<code>_NET_WM_STATE_REMOVE</code>	0	<code>/* remove/unset property */</code>
<code>_NET_WM_STATE_ADD</code>	1	<code>/* add/set property */</code>
<code>_NET_WM_STATE_TOGGLE</code>	2	<code>/* toggle property */</code>

See also the implementation notes on urgency and fixed size windows.

5.8. `_NET_WM_ALLOWED_ACTIONS`

```
_NET_WM_ALLOWED_ACTIONS, ATOM[ ]
```

A list of atoms indicating user operations that the Window Manager supports for this window. Atoms present in the list indicate allowed actions, atoms not present in the list indicate actions that are not supported for this window. The Window Manager **MUST** keep this property updated to reflect the actions which are currently "active" or "sensitive" for a window. Taskbars, Pagers, and other tools use `_NET_WM_ALLOWED_ACTIONS` to decide which actions should be made available to the user.

Possible atoms are:

```
_NET_WM_ACTION_MOVE, ATOM
_NET_WM_ACTION_RESIZE, ATOM
_NET_WM_ACTION_MINIMIZE, ATOM
_NET_WM_ACTION_SHADE, ATOM
_NET_WM_ACTION_STICK, ATOM
_NET_WM_ACTION_MAXIMIZE_HORZ, ATOM
_NET_WM_ACTION_MAXIMIZE_VERT, ATOM
_NET_WM_ACTION_FULLSCREEN, ATOM
_NET_WM_ACTION_CHANGE_DESKTOP, ATOM
_NET_WM_ACTION_CLOSE, ATOM
```

An implementation **MAY** add new atoms to this list. Implementations without extensions **MUST** ignore any unknown atoms, effectively removing them from the list. These extension atoms **MUST NOT** start with the prefix `_NET`.

Note that the actions listed here are those that the *Window Manager* will honor for this window. The operations must still be requested through the normal mechanisms outlined in this specification. For example, `_NET_WM_ACTION_CLOSE` does not mean that clients can send a `WM_DELETE_WINDOW` message to this window; it means that clients can use a `_NET_CLOSE_WINDOW` message to ask the Window Manager to do so.

Window Managers **SHOULD** ignore the value of `_NET_WM_ALLOWED_ACTIONS` when they initially manage a window. This value may be left over from a previous Window Manager with different policies.

`_NET_WM_ACTION_MOVE` indicates that the window may be moved around the screen.

`_NET_WM_ACTION_RESIZE` indicates that the window may be resized. (Implementation note: Window Managers can identify a non-resizable window because its minimum and maximum size in `WM_NORMAL_HINTS` will be the same.)

`_NET_WM_ACTION_MINIMIZE` indicates that the window may be iconified.

`_NET_WM_ACTION_SHADE` indicates that the window may be shaded.

`_NET_WM_ACTION_STICK` indicates that the window may have its sticky state toggled (as for `_NET_WM_STATE_STICKY`). Note that this state has to do with viewports, not desktops.

`_NET_WM_ACTION_MAXIMIZE_HORZ` indicates that the window may be maximized horizontally.

`_NET_WM_ACTION_MAXIMIZE_VERT` indicates that the window may be maximized vertically.

`_NET_WM_ACTION_FULLSCREEN` indicates that the window may be brought to fullscreen state.

`_NET_WM_ACTION_CHANGE_DESKTOP` indicates that the window may be moved between desktops.

`_NET_WM_ACTION_CLOSE` indicates that the window may be closed (i.e. a `WM_DELETE_WINDOW` message may be sent).

5.9. `_NET_WM_STRUT`

`_NET_WM_STRUT`, left, right, top, bottom, `CARDINAL[4]/32`

This property **MUST** be set by the Client if the window is to reserve space at the edge of the screen. The property contains 4 cardinals specifying the width of the reserved area at each border of the screen. The order of the borders is left, right, top, bottom. The client **MAY** change this property at any time, therefore the Window Manager **MUST** watch out for property notify events.

The purpose of struts is to reserve space at the borders of the desktop. This is very useful for a docking area, a taskbar or a panel, for instance. The Window Manager should know about this reserved space in order to be able to preserve the space. Also maximized windows should not cover that reserved space.

Rationale: A simple "do not cover" hint is not enough for dealing with e.g. auto-hide panels.

Notes: An auto-hide panel **SHOULD** set the strut to be its minimum, hidden size. A "corner" panel that does not extend for the full length of a screen border **SHOULD** only set one strut.

5.10. `_NET_WM_ICON_GEOMETRY`

`_NET_WM_ICON_GEOMETRY`, x, y, width, height, `CARDINAL[4]/32`

This optional property **MAY** be set by stand alone tools like a taskbar or an iconbox. It specifies the geometry of a possible icon in case the window is iconified.

Rationale: This makes it possible for a Window Manager to display a nice animation like morphing the window into its icon.

5.11. `_NET_WM_ICON`

`_NET_WM_ICON` `CARDINAL[][2+n]/32`

This is an array of possible icons for the client. This specification does not stipulate what size these icons should be, but individual desktop environments or toolkits may do so. The Window Manager **MAY** scale any of these icons to an appropriate size.

This is an array of 32bit packed `CARDINAL` ARGB with high byte being A, low byte being B. The first two cardinals are width, height. Data is in rows, left to right and top to bottom.

5.12. `_NET_WM_PID`

`_NET_WM_PID` `CARDINAL/32`

If set, this property **MUST** contain the process ID of the client owning this window. This **MAY** be used by the Window Manager to kill windows which do not respond to the `_NET_WM_PING` protocol.

If `_NET_WM_PID` is set, the ICCCM-specified property `WM_CLIENT_MACHINE` **MUST** also be set. While the ICCCM only requests that `WM_CLIENT_MACHINE` is set “to a string that forms the name of the machine running the client as seen from the machine running the server” conformance to this specification requires that `WM_CLIENT_MACHINE` be set to the fully-qualified domain name of the client’s host.

See also the implementation notes on killing hung processes.

5.13. `_NET_WM_HANDLED_ICONS`

`_NET_WM_HANDLED_ICONS`

This property can be set by a Pager on one of its own toplevel windows to indicate that the Window Manager need not provide icons for iconified windows, for example if it is a taskbar and provides buttons for iconified windows.

6. Window Manager Protocols

6.1. `_NET_WM_PING`

This protocol allows the Window Manager to determine if the Client is still processing X events. This can be used by the Window Manager to determine if a window which fails to close after being sent `WM_DELETE_WINDOW` has stopped responding or has stalled for some other reason, such as waiting for user confirmation. A Client **SHOULD** indicate that it is willing to participate in this protocol by listing `_NET_WM_PING` in the `WM_PROTOCOLS` property of the client window.

A Window Manager can use this protocol at any time by sending a client message as follows:

```
type = ClientMessage
window = the respective client window
message_type = WM_PROTOCOLS
format = 32
data.l[0] = _NET_WM_PING
data.l[1] = timestamp
```

A participating Client receiving this message **MUST** send it back to the root window immediately, by setting `window = root`, and calling `XSendEvent`. The Client **MUST NOT** alter the timestamp, as this can be used by the Window Manager to uniquely identify the ping.

The Window Manager **MAY** kill the Client (using `_NET_WM_PID`) if it fails to respond to this protocol within a reasonable time.

See also the implementation notes on killing hung processes.

7. Implementation notes

7.1. Desktop/workspace model

This spec assumes a desktop model that consists of one or more completely independent desktops which may or may not be larger than the screen area. When a desktop is larger than the screen it is left to the Window Manager if it will implement scrolling or paging.

7.2. File Manager desktop

This spec suggests implementing the file manager desktop by mapping a desktop-sized window (no shape) to all desktops, with `_NET_WM_WINDOW_TYPE_DESKTOP`. This makes the desktop focusable and greatly simplifies implementation of the file manager. It is also faster than managing lots of small shaped windows. The file manager draws the background on this window. There should be a root property with a window handle for use in applications that want to draw the background (xearth).

7.3. Implementing enhanced support for application transient windows

If the `WM_TRANSIENT_FOR` property is set to None or Root window, the window should be treated as a transient for all other windows in the same group. It has been noted that this is a slight ICCCM violation, but as this behavior is pretty standard for many toolkits and window managers, and is extremely unlikely to break anything, it seems reasonable to document it as standard.

7.4. Urgency

Dialog boxes should indicate their urgency level (information or warning) using the urgency bit in the `WM_HINTS.flags` property, as defined in the ICCCM.

7.5. Fixed size windows

Windows can indicate that they are non-resizable by setting `minheight = maxheight` and `minwidth = maxwidth` in the ICCCM `WM_NORMAL_HINTS` property. The Window Manager MAY decorate such windows differently.

7.6. Pagers and Taskbars

This specification attempts to make reasonable provisions for window manager independent pagers and taskbars. Window Managers that require / desire additional functionality beyond what can be achieved using the mechanisms set out in this specification may choose to implement their own pagers, which communicate with the Window Manager using further, window manager specific hints, or some other means.

Pagers should decide whether to show a miniature version of a window using the following guidelines:

- If either `_NET_WM_STATE_SKIP_PAGER` or `_NET_WM_STATE_HIDDEN` are set on a window, then the pager should not show that window.
- The pager may choose not to display windows with certain semantic types; this spec has no recommendations, but common practice is to avoid displaying `_NET_WM_WINDOW_TYPE_DOCK` for example.
- If the `_NET_WM_STATE_SKIP_PAGER` and `_NET_WM_STATE_HIDDEN` hints are not present, and the Window Manager claims to support `_NET_WM_STATE_HIDDEN`, then the window should be shown if it's in either `NormalState` or `IconicState`.
- For Window Managers that do not support `_NET_WM_STATE_HIDDEN`, the pager should not show windows in `IconicState`. These Window Managers are probably using an older version of this specification.

7.7. Window Movement

Window manager implementors should refer to the ICCCM for definitive specifications of how to handle `MapRequest` and `ConfigureRequest` events. However, since these aspects of the ICCCM are easily misread, this document offers the following clarifications:

- Window managers **MUST** honor the `win_gravity` field of `WM_NORMAL_HINTS` for both `MapRequest` and `ConfigureRequest` events (ICCCM Version 2.0, §4.1.2.3 and §4.1.5)
- Applications are free to change their `win_gravity` setting at any time.

If an application changes its gravity then the Window Manager should adjust the reference point, so that the client window will not move as the result. For example if Client's gravity was `NorthWestGravity` and reference point was at the top-left corner of the frame window, then after change of gravity to the `SouthEast` reference point should be adjusted to point to the lower-right corner of the frame.

- When generating synthetic `ConfigureNotify` events, the position given **MUST** be the top-left corner of the client window in relation to the origin of the root window (i.e., ignoring `win_gravity`) (ICCCM Version 2.0, §4.2.3)
- `XMoveWindow(w,x,y)` behavior depends on the window gravity. Upon receiving a request from a client application the Window Manager calculates a new reference point, based on the client window's own size, border width and gravity. For any given client window dimensions (width, height) and border width (bw), the reference point will be placed at:

Gravity:	ref_x:	ref_y:
<code>StaticGravity</code>	x	y
<code>NorthWestGravity</code>	x-bw	y-bw
<code>NorthGravity</code>	x+(width/2)	y-bw

NorthEastGravity	$x + \text{width} + \text{bw}$	$y - \text{bw}$
EastGravity	$x + \text{width} + \text{bw}$	$y + (\text{height}/2)$
SouthEastGravity	$x + \text{width} + \text{bw}$	$y + \text{height} + \text{bw}$
SouthGravity	$x + (\text{width}/2)$	$y + \text{height} + \text{bw}$
SouthWestGravity	$x - \text{bw}$	$y + \text{height} + \text{bw}$
WestGravity	$x - \text{bw}$	$y + (\text{height}/2)$
CenterGravity	$x + (\text{width}/2)$	$y + (\text{height}/2)$

The Window Manager will use the reference point as calculated above, until the next XMoveWindow request. The Window Manager will place frame decorations in the following position, based on the window gravity :

StaticGravity:

window's left top corner will be placed at (ref_x,ref_y)

NorthWestGravity:

window frame's left top corner will be placed at (ref_x,ref_y)

NorthGravity:

window frame's top side's center will be placed at (ref_x,ref_y)

NorthEastGravity:

window frame's right top corner will be placed at (ref_x,ref_y)

EastGravity:

window frame's right side's center will be placed at (ref_x,ref_y)

SouthWestGravity:

window frame's left bottom corner will be placed at (ref_x,ref_y)

SouthGravity:

window frame's bottom side's center will be placed at (ref_x,ref_y)

SouthEastGravity:

window frame's right bottom corner will be placed at (ref_x,ref_y)

WestGravity:

window frame's left side's center will be placed at (ref_x,ref_y)

CenterGravity:

window frame's center will be placed at (ref_x,ref_y)

- Implementation Note for Application developers:

When a client window is resized - its reference point does not move. So for example if window has SouthEastGravity and it is resized - the bottom-right corner of its frame will not move but instead top-left corner will be adjusted by the difference in size.

- Implementation Note for window manager developers:

When calculating the reference point at the time of initial placement - the initial window's width should be taken into consideration, as if it was the frame for this window.

7.8. Window-in-Window MDI

The authors of this specification acknowledge that there is no standard method to allow the Window Manager to manage windows that are part of a Window-in-Window MDI application. Application authors are advised to use some other form of MDI, or to propose a mechanism to be included in a future revision of this specification.

7.9. Killing Hung Processes

If processes fail to respond to the `_NET_WM_PING` protocol `_NET_WM_PID` may be used in combination with the ICCCM specified `WM_CLIENT_MACHINE` to attempt to kill a process.

`WM_CLIENT_MACHINE` is usually set by calling `XSetWMProperties()`. The hostname for the current host can be retrieved using `gethostname()`, when `gethostname()` is not available on the platform implementors may use the value of the `nodename` field of `struct utsname` as returned by `uname()`. Note also that the value of `WM_CLIENT_MACHINE` is not guaranteed to be a fully fully-qualified domain name of the host. An example of how to retrieve the hostname:

```
int net_get_hostname (char *buf, size_t maxlen)
{
#ifdef HAVE_GETHOSTNAME
    if (buf == NULL) return 0;

    gethostname (buf, maxlen);
    buf [maxlen - 1] = '\0';

    return strlen(buf);
#else
    struct utsname name;
    size_t len;

    if (buf == NULL) return 0;

    uname (&name);
    len = strlen (name.nodename);

    if (len >= maxlen) len = maxlen - 1;
    strncpy (buf, name.nodename, len);
    buf[len] = '\0';

    return len;
#endif
}
```



```
#endif
}
```

7.10. Stacking order

To obtain good interoperability between different Desktop Environments, the following layered stacking order is recommended, from the bottom:

- windows of type `_NET_WM_TYPE_DESKTOP`
- windows having state `_NET_WM_STATE_BELOW`
- windows not belonging in any other layer
- windows of type `_NET_WM_TYPE_DOCK` (unless they have state `_NET_WM_STATE_BELOW`) and windows having state `_NET_WM_STATE_ABOVE`
- focused windows having state `_NET_WM_STATE_FULLSCREEN`

Windows that are transient for another window should be kept above this window.

The window manager may choose to put some windows in different stacking positions, for example to allow the user to bring currently a active window to the top and return it back when the window loses focus.

8. References

[UTF8]

F. Yergeau, "UTF-8, a transformation format of ISO 10646", RFC 2279

[ICCCM]

David Rosenthal and Stuart W. Marks, "Inter-Client Communication Conventions Manual (Version 2.0)", X Consortium Standard, X Version 11, Release 6.3

9. Copyright

Copyright (C) 2000, 2001, 2002 See Contributors List

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell

copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

10. Contributors

Sasha Vasko

Bradley T. Hughes

Dominik Vogt

Havoc Pennington

Jeff Raven

Jim Gettys

John Harper

Julian Adams

Matthias Ettrich

Micheal Rogers

Nathan Clemons

Tim Janik

Tomi Ollila

Sam Lantinga

The Rasterman

Paul Warren

Owen Taylor

Marko Macek

Greg Badros

Matthias Clasen

David Rosenthal

Lubos Lunak

11. Change history

11.1. Changes since 1.1

- Changed WM_CLIENT_NAME(String) from suggested to required for _NET_WM_PID.
- Specification and sample code for the content of WM_CLIENT_NAME(String).
- Added _NET_WM_WINDOW_TYPE_SPLASH, _NET_WM_WINDOW_TYPE_UTILITY.
- Added _NET_WM_STATE_FULLSCREEN.
- Added _NET_WM_ALLOWED_ACTIONS.
- Added _NET_WM_STATE_HIDDEN and clarified purpose of _NET_WM_STATE_SKIP_PAGER and _NET_WM_STATE_SKIP_TASKBAR. Changed section on virtual desktop implementation to suggest ICCCM compliance regarding IconicState, using _NET_WM_STATE_HIDDEN to avoid confusion. Added implementation note for pagers on when to display a window.
- Added button field and new directions for keyboard-initiated actions to the _NET_WM_MOVERESIZE message.
- Added advice on removing _NET_WM_STATE and _NET_WM_DESKTOP when a window is withdrawn.
- Added _NET_DESKTOP_LAYOUT to allow a Pager to specify inter-desktop geometry.
- Added _NET_SHOWING_DESKTOP.
- Added _NET_WM_STATE_ABOVE and _NET_WM_STATE_BELOW and a recommended layered stacking order.
- Added _NET_MOVERESIZE_WINDOW.
- Improve markup of citations.
- Explain _NET_DESKTOP_GEOMETRY and _NET_WM_HANDLED_ICONS in more detail and improve the explanation of WM_CLIENT_MACHINE in Section 7.9.
- Add Lubos Lunak to the list of contributors.

11.2. Changes since 1.0

- Fix doctype, add author info, update data.
- Change specification description wording to be more inclusive, and to reflect the joint nature of the specification.
- Fix miscellaneous typographical, grammar and spelling errors.
- Clarified _NET_SUPPORTED to include ALL atoms, not just the property names.
- Various corrections to use of MUST and SHOULD.
- Fix problem in _NET_WM_ICON where 'bytes' should have been 'cardinals'

- Replaced ISO-8559-1 characters with entities.

11.3. Changes since 1.0pre5

- Change history moved to end.
- UTF-8 Reference updated.
- Window Gravity information updated.
- Copyright Added.
- Minor typo corrections.

11.4. Changes since 1.0pre4

- Clarified the interpretation of client-provided geometries on large desktops.
- Added more explanation for `_NET_DESKTOP_NAMES`.
- Added `_NET_WM_ICON_NAME` and `_NET_WM_VISIBLE_ICON_NAME`.
- Tried to improve the wording of `_NET_WM_STRUT` explanation.
- Changed `_NET_WORKAREA` to an array of viewport-relative geometries.
- Updated list of “dependent” properties for `_NET_NUMBER_OF_DESKTOPS` to include `_NET_WORKAREA` and `_NET_DESKTOP_VIEWPORT`.
- Tidied formatting of all client messages.

11.5. Changes since 1.0pre3

- Added information about common non-ICCCM features.
- Added explanation of sending messages to the root window.
- Removed `XA_` prefix from type names.
- Clarified that “mapping order” refers to initial mapping and specify the directions of both orders.
- Clarified that desktops have a common size specified by `_NET_DESKTOP_GEOMETRY`.
- Rewrote explanation of `_NET_DESKTOP_VIEWPORT`.
- Tidied formatting of `_NET_CURRENT_DESKTOP`.
- Replaced “window handle” by “window ID”.
- Tidied formatting of `_NET_WORKAREA`.
- Rewrote the motivation for `_NET_VIRTUAL_ROOTS`.
- Added advice on Pointer grabs to `_NET_WM_MOVERESIZE`.

- Fixed typos in `_NET_WM_STATE`.
- Added `_NET_WM_STATE_SKIP_PAGER`.
- Tidied formatting of `_NET_WM_STRUT`.
- Tidied formatting of `_NET_WM_ICON_GEOMETRY`.

11.6. Changes since 1.0pre2

- `_NET_SET_NUMBER_OF_DESKTOPS` -> `_NET_NUMBER_OF_DESKTOPS` for consistency.
- `_NET_WM_VISIBLE_NAME_STRING` -> `_NET_WM_VISIBLE_NAME` for consistency.
- `_NET_WM_STATE`: added explanation of permitted extensions. Added explanation of being set / not set.
- Spellchecked, corrected various typos.
- UTF8 -> UTF-8 for consistency.
- added references to the ICCCM an UTF-8 (incomplete).
- added data and event formats where missing.
- clarified `_NET_SUPPORTING_WM_CHECK`.
- fixed formatting of `_NET_CLOSE_WINDOW` message.

11.7. Changes since 1.0pre1

- Removed implementation note concerning Gnome's (potential) file manager behavior.
- The Window Movement section of the implementation notes has been revised.

11.8. Changes since 1.9f

- Revised revision number for first accepted release 1.9XX -> 1.0preXX.
- Prerequisites for adoption of this specification added.
- Tidied formatting of `_NET_CURRENT_DESKTOP` for consistency.
- Tidied formatting of `_NET_ACTIVE_WINDOW` for consistency. Removed doubled text.
- Tidied formatting of `_NET_WM_DESKTOP` for consistency.
- Killing Hung Processes implementation note added. `_NET_WM_PID` and `_NET_WM_PING` now link to this.
- Clarified `x_root` and `y_root` meaning for `_NET_WM_MOVERESIZE`.
- Added contributor list.

11.9. Changes since 1.9e

- Added `_NET_WM_VISIBLE_NAME_STRING`
- Removed ambiguity from `_NET_NUMBER_OF_DESKTOPS` and `_NET_DESKTOP_NAMES` in combination.
- Set `_NET_WM_MOVERESIZE` format to 32 for consistency.
- Removed `_NET_PROPERTIES`.
- Removed comment from `_NET_WM_MOVERESIZE`.

11.10. Changes since 1.9d

- Added `_NET_VIRTUAL_ROOTS`
- Added note about ICCCM compliant window moves.
- Added `_NET_WM_HANDLED_ICONS`
- Added `_NET_SUPPORTING_WM_CHECK`
- Removed degrees of activation

11.11. Changes since 1.9c

- Removed packaging of hints into 2 X properties. Jim Gettys points out that the performance gains of fewer round trips can be better achieved using Xlib routines.
- Clarified that `_NET_DESKTOP_VIEWPORT` is in pixels
- `_NET_DESKTOP_VIEWPORT` is now an array, one for each desktop, to allow for different active viewports on different desktops
- `_NET_WM_STRUT` now only applies on desktops on which the client is visible
- Introduced RFC 2119 language, and attempted to clarify the roles of the Window Manager, Pagers and Applications
- Added `_NET_WM_NAME`
- `_NET_DESKTOP_NAMES` now in UTF8
- Desktops now start from 0
- Added `_NET_WM_PID`
- Added `_NET_WM_PING` protocol
- Added `_NET_WM_STATE_SKIP_TASKBAR`

11.12. Changes since 1.9b

- Removed `_NET_NUMBER_OF_DESKTOPS` client message, as it overlaps unnecessarily with `_NET_{INSERT/DELETE}_DESKTOP`.
- Replaced `_NET_WM_LAYER` and `_NET_WM_HINTS` with `_NET_WM_WINDOW_TYPE` functional hint.
- Changed `_NET_WM_STATE` to a list of atoms, for extensibility.
- Expanded description of `_NET_WORKAREA` and `_NET_WM_STRUT`.
- Removed `_NET_WM_SIZEMOVE_NOTIFY` protocol.
- Added degrees of activation to `_NET_ACTIVE_WINDOW` client message
- Added `_NET_WM_ICON`
- My comments are in `[[]]`. Comments from Marko's draft are in `[[MM:]]`